

# 0、Color HSV value calibration

## 0、Color HSV value calibration

### 1 brief introduction

### 2 Core content analysis

### 3 Steps

## 1 brief introduction

In this course, we will focus on capturing camera images, selecting the corresponding color, and then adjusting its HSV value to achieve the best recognition effect.

This course mainly optimizes the recognition effect by modifying the HSV value of the image, and then provides more accurate HSV values to the routines related to color recognition.

Note: Since the HSV values calibrated by this tutorial are only stored in this routine directory, they need to be manually copied into the source code of the routine that needs to update the HSV values for this to work.

## 2 Core content analysis

g\_ENABLE\_CHINESE indicates the control Chinese character switch, the default is False for English characters, if you need to display Chinese, please set to True.

```
g_ENABLE_CHINESE = False
Name_widgets = {
    'Red': ("Red", "红色"),
    'Green': ("Green", "绿色"),
    'Blue': ("Blue", "蓝色"),
    'Yellow': ("Yellow", "黄色"),
    'Custom': ("Custom", "自定义"),
    'Close_Camera': ("Close_Camera", "关闭摄像头")
}
```

The range of color HSV values is shown in the following figure:

	black	grey	white	red	orange	yellow	green	light blue	blue	Purple
H_min	0	0	0	0	156	11	26	35	78	125
H_max	180	180	180	10	180	25	34	77	99	155
S_min	0	0	0	43	43	43	43	43	43	43
S_max	255	43	30	255	255	255	255	255	255	255
V_min	0	46	221	46	46	46	46	46	46	46
V_max	46	220	255	255	255	255	255	255	255	255

When the color button is clicked for the first time, the initial HSV value is used, and then the value of the slider needs to be adjusted based on the HSV value of the color to make the color more accurate, and the final effect is to accurately identify the color, but not confusing with other colors.

Initialize the hexapod robot, set the camera pan-tilt Angle, the default is S1=90, S2=0, the initial Angle can be modified according to the actual demand.

```
from MutoLib import Muto
g_bot = Muto()
g_bot.Gimbal_1_2(90, 0)
```

The default camera image resolution is 640\*480, and the display resolution can be modified to 320\*240 to reduce the image frame.


```
img_width = 320
img_height = 240
```

### 3 Steps

Open the jupyterLab client and find the code path:

```
muto/Samples/AI_Samples/00_color_hsv/color_hsv.ipynb
```

Click to run all cells, and then scroll to the bottom to see the generated controls.




The control displays three image boxes. The image control on the left displays the original image. The function of the image control in the middle is: the recognized color is displayed as white and other colors are displayed as black. The function of the image control on the right is: the recognized color is displayed normally and other colors are displayed. into black.

A single color can be put into the camera picture, but in order to get the HSV value more accurately, four colors, red, green, blue and yellow, can be put into the camera picture. Select a color among red, green, blue and yellow. At this time, a ✓ will appear to the left of the selected color. Please slightly adjust the six sliders to modify the value of the color HSV so that the selected color is displayed completely and does not differ from other colors. Mix the color blocks, then click on the corresponding color again to save the color HSV value to a local file. Each time you select a color, the local file will be read first. If the local file cannot be read, the default HSV value will be used. If you need to restore the default HSV value, please delete the HSV\_VALUE.TXT file of the corresponding color.


For example, red is selected here. If the color recognition is incomplete or wrong, please slightly adjust the six sliders to modify the value of the color HSV. When the color effect reaches the appropriate effect, click the red button again to save the current color HSV. value to a local file.




For example, the red color in the picture above is saved in the RED\_HSV\_VALUE.TXT file, where the HSV values are 0,59,81,10,255,255. Numerical representation: Hmin, Smin, Vmin, Hmax, Smax, Vmax. This value can be copied and updated to the HSV value of other routines.




The green HSV calibration effect is as follows. After calibration, please click the green button again to save the values to the GREEN\_HSV\_VALUE.TXT file.



The blue HSV calibration effect is as follows. After calibration, please click the blue button again to save the value to the BLUE\_HSV\_VALUE.TXT file.



The yellow HSV calibration effect is as follows. After calibration, please click the yellow button again to save the value to the YELLOW\_HSV\_VALUE.TXT file.



Customize the color button. After calibration, please click the custom button again to save the value to the CUSTOM\_HSV\_VALUE.TXT file.

Finally click the Close\_Camera button to close the camera.

Note: The TXT file of HSV values generated after calibration in this tutorial will not be automatically updated to all routines. You need to update and replace the HSV value variables in the program based on the values in the TXT file.